

Silent Installation of the DYMO Label Software

Answer 634 | Applies To DYMO | Published 04/23/2007 11:08 AM EDT | Updated 06/13/2013 01:53 PM EDT

What is the installation switch for running a silent install of the DYMO Label software in Windows?

DYMO Label v.8

1. Download the DYMO Label software installer.
 - To download the DYMO Label software installer, [click here](#) to be redirected to the **Drivers and Downloads** section.
2. Click **Start**, select **Run**, enter **CMD**, and click **OK**.
3. At the command prompt, change to the directory where the DYMO Label software installer is located
4. Enter the name of the DYMO Label software installer and add the appropriate switch command and press **Enter**. DYMO Label version 8 supports the following:
 - /P (printer drivers only)
 - /D (supported by NSIS for output directory /D=C:\temp (for instance) **Note:** it must be the last command-line parameter)
 - /S (for silent install/uninstall, to uninstall need to use the uninstall.exe file in the DYMO Label folder)

DYMO Label Software Version 7

1. Download the DYMO Label software installer.
 - To download the DYMO Label software installer, [click here](#) to be redirected to the **Drivers and Downloads** section.
2. Click **Start**, select **Run**, enter **CMD**, and click **OK**.
3. At the command prompt, change to the directory where the DYMO Label software installer is located
4. Enter the name of the DYMO Label software installer, without the .exe extension, add a /s switch and press **Enter**.
 - For example, if the name of the DYMO Label Software installer is **WIN_DLS77.exe**, the command option to enter is **WIN_DLS77 /s**

Note:

- You will be prompted to connect the LabelWriter for new installations.

- The installation will be completely silent if you are upgrading the DYMO Label Software and the LabelWriter is connected.